
#### **Configuring Windows Mail**

Default e-mail client for Windows Vista.

This document will help you configure Windows Mail to manage your Iglou E-Mail account.

Step 1

Open Windows Mail. Likely, you will have a screen that looks something like this:



Step 2

On the Tools menu, select Accounts. The Internet Accounts dialog will appear.

If you aren't going to be using this software for any other E-Mail service, remove any accounts that are there. If there are no mail accounts active in Windows Mail, the Mail subcategory will be missing.

News	□ 
Microsoft Communities (default) msnews.microsoft.com	<u></u> emove
Directory Service	Properties Set as Defaul
	Import
	Export
	Set Order

#### Step 3

Click the Add button. Select E-mail Account and then click the Next button.

	ز
Select Account Type What type of account would you like to add?	
What information do I need to set up my account?	Next Cancel

#### Step 4

You will be prompted to enter your name. Enter your name as you would like it to appear on messages you send out. When someone receives your mail, it will show that it came from whatever is entered here. When you're done, click Next.

Your Name		
When you send e-mail, y Type your name as you v	your name will appear in the From field of the outgoing message. would like it to appear.	
<u>D</u> isplay name:	John Doe	
	For example: John Smith	
Where can I find my e-m	ail account information?	
		_
	Next	Cancel

Step 5 Enter your E-Mail address Do this in the format username@iglou.com and click next when finished.

		×
Internet E-mail Address		
Your e-mail address is the address other people use to send e-mail messages to you.		
E-mail address: 1		
For example: someone@microsoft.com		
Where can I find my e-mail account information?		
	Haut	const 1
	Next	Cancel

Step 6

Now, you'll be asked to provide the names of the mail servers you use. Here is the information you need to know:

Your incoming mail server is a POP3 server.



Your incoming mail server is: pop.iglou.com

Your outgoing mail server is: smtp.iglou.com

Enter the information as shown here, check Outgoing Server Requires Authentication, and click Next when you've done this:

Set u	ıp e-mail servers
	Incoming e-mail server type:
	POP3
	Incoming mail (POP3 or IMAP) server:
2	
	Outgoing e-mail server (SMTP) name:
3	
	☑ Outgoing server requires authentication
	Where can I find my e-mail server information?

Step 7 Now you'll need to enter the following:

Your Account name (username) and password. Your Account name is the first part of your E-Mail address (everything before the @ symbol).

		USIN TANK STR
Internet Mail Logon		
Type the account name	and password your Internet service provider has given you.	
E-mail usern <u>a</u> me:	username	
e nine evenigine.	1	
Password:	••••••	
	Remember pass <u>w</u> ord	

Step 8 Now, click Finish to save all of your information.

	×
<b>G</b>	
Congratulations	
You have successfully entered all of th	ne information required to set up your account.
To save these settings and download	your e-mail, click Finish.
Do not download my e-mail at	this time
	Enish Cancel

Step 9

You'll notice that the Internet Accounts dialog box now shows our mail server as being installed. Click the Properties button and then the Servers tab.

**4** This will indicate your mailbox name in Windows Mail.

Mail	
pop.iglou.com (default) 4	<u>Add</u>
News	
Microsoft Communities (default)	Propertie
msnews.microsoft.com	Set as Defa
Directory Service	Import
	Export
	<u>S</u> et Order

#### Step 10

On the servers page you will notice that the Incoming and Outgoing mail server information has already been filled in. Place a check next to "My server requires authentication". Click the Settings button.

**2** Your incoming mail server is: pop.iglou.com

**3** Your outgoing mail server is smtp.iglou.com

General Servers Connection Security	Advanced	
Server Information		
My incoming mail server is a P	OP3 server.	
Outgoing mail (SMTP): 3		
Incoming Mail Server		
E-mail usem <u>a</u> me:		
Password:		
Remer	mber pass <u>w</u> ord Authentication	
Outgoing Mail Server		
✓ My server requires authenticatio	on <u>Settings</u>	

#### Step 11

Select the "Log on using" option and enter your E-Mail address and password where indicated.

5 Your Account Name is your full E-Mail address (ex. username@iglou.com)

ogon Information —	
C Use same setting	gs as my incoming mail server
Log on using	
<u>E</u> -mail usemame	= <mark>5</mark>
Password:	
	Remember password
	Secure Password Authentication
🔲 Log on using	Secore Lassmord Addientication

Click OK and then OK again. At the "Internet Accounts" dialog box, click the Close button. Windows Mail is now configured to work with our mail server.

Helpful Pointers for using Windows Mail:

Windows Mail automatically checks for new messages periodically while the program is open and you are connected to our service. If at any given time you want to force the software to check for messages immediately, simply click the Send and Receive button.

If Windows Mail seems to hang while sending and receiving messages, you can restart that process by telling it to Stop and then click Send and Receive again.

To write a new message, simply click on the Create Mail button. Make sure you enter in the full Internet E-Mail address correctly to ensure the message gets where it's supposed to go.

When replying to a message, just click the normal Reply button. This will send your reply to the author of the message that you're replying to.

If a message you're replying to was sent to a group of people, you can click the Reply to All button to send your reply to everyone on the list, but it is advised that you do this only when necessary.

Unique solution ID: #1073 Author: n/a Last update: 2015-05-22 19:00